

OVERVIEW

The new ORION Mobile Read (OMR) can be installed on most Windows® based devices including the Trimble® Ranger 7, Yuma 7 and tablet. It can also be installed on the Panasonic® tablets and laptops, and any Windows device you purchased.

NOTE: It does not work on the legacy Trimble Ranger 3.

Windows Update

Before you begin the process, make sure to check for and install any Windows updates. Your Windows Update screen should look similar to [Figure 1](#).




Figure 1: Windows Update

STEP ONE: DOWNLOAD THE NEW OMR SOFTWARE FROM BEACON®

1. Log into BEACON and go to **Utility Settings>Downloads**.
2. Locate **ORION® Mobile Read (OMR)** under Device Applications and click the **Download** button.
3. Make sure the download is complete and saved in a location you can access.




Figure 2: ORION Mobile Read download

STEP TWO: INSTALL THE SOFTWARE ONTO YOUR DEVICE

1. Open the location where you saved the OMR.exe file.
2. Double click on the .exe file to begin the install process ([Figure 3](#)).

NOTE: You may need admin privileges to install the software.

3. The setup wizard opens ([Figure 4](#)). Click **Next**.




Figure 3: OMR.exe file




Figure 4: OMR Setup Wizard

4. Confirm the location shown for the installation folder.
5. If multiple users will access this device, select the **Everyone** radio button ([Figure 5](#)). For individual users, select **Just me**.
6. Click **Next** to confirm.
7. Click **Next** again to start the installation. The installation process will run.
8. When the process is complete, click **Close** ([Figure 6](#)).




Figure 5: Installation folder location




Figure 6: OMR installation complete

STEP THREE: LAUNCH THE SOFTWARE

1. Go to Windows Start menu and search OMR.
2. Click on the OMR icon to start the software.
3. Use your BEACON credentials to log into the software.
4. Read and acknowledge the initial warning.

You are ready to begin using OMR.

Additional Resources

For additional information, refer to the ORION Mobile Read Quick Start Guide, available at [badgermeter.com](https://www.badgermeter.com).

SMART WATER IS BADGER METER

BEACON and ORION are registered trademarks of Badger Meter, Inc. Other trademarks appearing in this document are the property of their respective entities. Due to continuous research, product improvements and enhancements, Badger Meter reserves the right to change product or system specifications without notice, except to the extent an outstanding contractual obligation exists. © 2024 Badger Meter, Inc. All rights reserved.

www.badgermeter.com